


# Pursuit 7 for Windows

**Proposal Generation System**

**Z-Micro Technologies, Inc.**




## Installation Guide

*Copyright 2010. Z-Micro Technologies, LLC. All Rights Reserved.*

## Setting Up Pursuit 7 for Windows - Client Setup

**PLEASE NOTE:** YOU WILL NEED TO MAP A NETWORK DRIVE TO THE ALARMWIN DATABASE FOLDER BEFORE SETTING UP PURSUIT. IF YOU PLAN ON USING PURSUIT 7 AS A STAND-ALONE PRODUCT YOU WILL NOT NEED A MAPPED DRIVE TO THE ALARMWIN DATABASE.


**Step 1.** To install Pursuit for windows, double left click on setup.exe. Follow along using the install wizard, you can leave all setting at their default selection. The default install directory is C:\Pursuit 7. If you would like to change to another drive or folder, you can change the installation directory during the setup wizard (see Figure 1.0).




**Figure 1.0**

If you are setting up Pursuit 7 on a workstation go to the next step if you are setting up a server or main computer go to **step 7**.

**Step 2.** Next you will need to map a network drive to your Pursuit data on your server or main computer. Go to **START > COMPUTER** or **MY COMPUTER** on the left hand side panel (Other Places) select **NETWORK** or **MY NETWORK PLACES** (see Figure 3.0). If you do **NOT** see the Pursuit 7 shared folder here go to **step 3**. If you **DO** see the Pursuit 7 shared folder go to **step 4**.




**Figure 2.0**




**Figure 3.0**

**Step 3.** Click on VIEW WORKGROUP COMPUTERS from the Network Tasks panel on the left. This will show you a list of all the computers on your network (see Figure 5.0). Find the server or main computer then double click on it.




**Figure 4.0**



**Figure 5.0**

You should now see a list of available shared folders (See Figure 6.0). Highlight the PURSUIT7 shared folder. If you have shared the folder as a different name i.e. Pursuit or Pursuit 2007, just select that folder. Go to **Step 4**.




**Figure 6.0**

**Step 4.** Go to TOOLS on the menu bar and then select MAP NETWORK DRIVE (See Figure 7.0).



**Figure 7.0**



**Figure 8.0**


From the DRIVE: drop down select the letter you would like to assign to the drive mapping (in our example letter W:\ ). From the FOLDERS selection box click on the BROWSE... button (See Figure 8.0) from the list of shared folders select the PURSUIT7 folder on your server or main computer, then click ok. Go to step 5.

**Step 5.** From the MAP NETWORK DRIVE window make sure RECONNECT AT LOGON is CHECKED. Then click finish.




**Figure 9.0**

**Step 6.** Now we need to create a desktop short cut to the Pursuit program. Go to START > MY COMPUTER double left click on C:\ or Local disk C. Then double click on the Pursuit7 folder. Find Pursuit.exe right click on it then click on SEND TO > DESKTOP – CREATE SHORTCUT. Close or minimize all your windows so you can see your desktop. Find the Shortcut to Pursuit icon. Right click on it and then left click on properties (See Figure 10.0)




**Figure 10.0**



**Figure 11.0**

Once the properties window opens find the START IN: section (highlighted) and change the drive letter to the mapped drive letter you selected from step 4. In most cases you do NOT need to add the word PURSUIT after the drive letter W:\ (from our example). Finally click on APPLY then click OK.

**Step 7.** Double click or launch the Pursuit 7 program from the desktop shortcut. Once in the program go to UTILITIES and left click on RESET ALARM INTEGRATION PATHS FOR THIS WORKSTATION ONLY (Figure 12.0).



**Figure 12.0**

You will then be asked if you will be integrating Pursuit with Alarm or Service Express. Please click the drop-down box and select YES (Figure 13).




**Figure 13.0**

**Step 8.** Double click or launch the Pursuit 7 program from the desktop shortcut. Once in the program go to UTILITIES and left click on RESET ALARM INTEGRATION PATHS FOR THIS WORKSTATION ONLY (Figure 12.0).

In the SELECT LOCATION OF ALARM DATA FILES (Network) enter the drive letter for your mapped drive to the Alarm for Windows database folder.

In the SELECT LOCATION OF ALARM DATA FILES (Local) enter C:\Alarmwin (the default) if you have Alarm for Windows installed in another directory i.e. D:\Alarmwin enter it here.

In the SELECT LOCATION OF PURSUIT 7 DATA FILES enter the drive letter of the mapped drive from Step 4. Then click OK.



**Figure 14.0**

To double check you are linked to the Alarm database click on INVENTORY from the menu bar in Pursuit, you should see a list of the inventory items in the Alarm for windows database. You can now use Pursuit 7 for Windows.